

Lecture 1

01/17/2018

Review of Electrostatics

Equations:

$$\vec{\nabla} \cdot \vec{E} = \frac{\rho}{\epsilon_0} \quad *$$

$\rho$ : volume charge density

$$\vec{\nabla} \times \vec{E} = 0 \quad **$$

From the second equation \*\*, we find:

$$\vec{E} = -\vec{\nabla} \Phi \quad \Phi: \text{electric potential}$$

This gives rise to Poisson's equation:

$$\nabla^2 \Phi = -\frac{\rho}{\epsilon_0}$$

In unbounded space, the solution to this equation is:

$$\Phi(\vec{x}) = \int \frac{\rho(\vec{x}') d\vec{x}'}{4\pi\epsilon_0 |\vec{x} - \vec{x}'|} \quad \text{Volume element (also } dV')$$

For  $N$  point charges at  $\vec{x}_1, \dots, \vec{x}_N$ ,  $\rho(\vec{x}) = \sum_{i=1}^N q_i \delta(\vec{x} - \vec{x}_i)$ , and hence:

$$\Phi(\vec{x}) = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^N \frac{q_i}{|\vec{x} - \vec{x}_i|}$$

The first equation \* results in Gauss's law:

(2)

$$\oint_S \vec{E} \cdot d\vec{a} = \int_V \vec{\nabla} \cdot \vec{E} \, d\tau = \frac{1}{\epsilon_0} \int_V \rho \, d\tau = \frac{Q_{enc}}{\epsilon_0}$$

Here,  $Q_{enc}$  is the total charge enclosed in the volume  $V$  by  $S$ .

Gauss's law is most useful when symmetries of the problem


permit its use in calculating the electric field  $\vec{E}$  directly.

### Poisson Equation in Bounded Space

Consider a finite volume  $V$  bounded by a surface  $S$ ;

In this case, arriving at a

single solution requires



pre-specified boundary conditions

on  $S$ . Such a well posed problem is obtained for a given

$\rho(\vec{x})$  distribution provided that either;

(1) the potential  $\Phi$  is specified on  $S$ , i.e.,  $\Phi|_S$  is given, or

(2) the normal derivative  $\frac{\partial \Phi}{\partial n}|_S$  is given on  $S$ , or

(3) the mixed condition  $(\alpha \Phi + \beta \frac{\partial \Phi}{\partial n})|_S$  is given on  $S$ ,

These problems, called Dirichlet, Neumann, and mixed prob<sup>lems</sup> respectively, have a unique solution.

Work By Electrostatic Field

$$\Delta W_e = \int_1^2 q \vec{E} \cdot d\vec{e} = -q \int_1^2 \vec{\nabla} \Phi \cdot d\vec{e} = -q \Phi|_1^2 = -q \Delta \Phi = -\Delta U_e$$

For static problems kinetic energy is zero. electrostatic potential

Hence, from the work-energy theorem, we have:

$$\Delta K = \Delta W_{e+} + \underbrace{\Delta W_{non-el}}_{\substack{\uparrow \\ \text{work by non-electrostatic forces}}} = 0 \Rightarrow -\Delta U_e + \Delta W_{non-el} = 0 \Rightarrow$$


$$\Delta U_e = \Delta W_{non-el}$$

Elementary Charge Configurations

(1) Point charge q at  $\vec{x}_1$ :

$$\Phi(\vec{x}) = \frac{q}{4\pi\epsilon_0 |\vec{x} - \vec{x}_1|}, \quad \vec{E}(\vec{x}) = \frac{q(\vec{x} - \vec{x}_1)}{4\pi\epsilon_0 |\vec{x} - \vec{x}_1|^3}$$

(2) Point dipole at the origin:




$$\vec{p} = q\vec{a} \quad (q \rightarrow \infty, |\vec{a}| \rightarrow 0, q|\vec{a}| \text{ fixed})$$

$$\Phi(\vec{x}) = \frac{\vec{p} \cdot \vec{x}}{4\pi\epsilon_0 |\vec{x}|^3}$$

$$\vec{E} = -\vec{\nabla} \Phi = \frac{1}{4\pi\epsilon_0} \frac{[3(\vec{p} \cdot \hat{n})\hat{n} - \vec{p}]}{|\vec{x}|^3} \quad \hat{n} = \frac{\vec{x}}{|\vec{x}|}$$

The expression is not valid at  $\vec{x}=0$  since there is a  $\delta$ -function term involved (which we will consider later).

(3) Charge layer:



Non-zero surface charge density

$$\sigma = \frac{\text{charge on the surface}}{\text{area on the surface}}$$

At the surface, we have:

$$\Delta E_n = E_{1n} - E_{2n} = \frac{\sigma}{\epsilon_0}$$


However, potential is continuous at the surface ( $\Phi_1 = \Phi_2$ )

in order to have finite electric field.

(4) Dipole layer:

$$\text{Non-zero surface dipole density } \mathbf{D} = \frac{\text{dipole moment on the surface}}{\text{area of the surface}}$$


$$\Phi(\vec{x}) = \frac{1}{4\pi\epsilon_0} \int_S \frac{\vec{D}(\vec{x}') \cdot d\vec{a}' \cdot (\vec{x} - \vec{x}')}{|\vec{x} - \vec{x}'|^3}$$



For a uniform dipole layer  $|\vec{D}|$  is constant, and hence:

$$\Phi(\vec{x}) = \frac{D}{4\pi\epsilon_0} \int_S \frac{\hat{n}' \cdot (\vec{x} - \vec{x}')}{|\vec{x} - \vec{x}'|^3} da'$$

$$\frac{\hat{n}' \cdot (\vec{x} - \vec{x}') da'}{|\vec{x} - \vec{x}'|^3} = \frac{\cos\theta' da'}{|\vec{x} - \vec{x}'|^2} = d\Omega' \leftarrow \text{solid angle subtended by } S \text{ at observation point } \vec{x}$$



Therefore:

$$\Phi(\vec{x}) = \frac{D}{4\pi\epsilon_0} \Delta\Omega$$

Note, however, that for  $\vec{x}$  below the surface, we have:

$$\Phi(\vec{x}) = \frac{D}{4\pi\epsilon_0} (-\Delta\Omega)$$

This is because  $\cos\theta'$  in this case is negative.

As a result, at the surface, we have:

$$\Phi|_{s^+} - \Phi|_{s^-} = \frac{D}{2\pi\epsilon_0} \Delta\Omega = \frac{D}{\epsilon_0} \quad (\Delta\Omega = 2\pi)$$

$\Phi$  discontinuous at a dipole layer